

LAB 7


Virtual PC

Download a free version from:

<http://www.microsoft.com/en-gb/download/details.aspx?id=4580>


Install it on your PC (Win8 not supported!).

Open a click New->New Virtual Machine Wizard



General Networking

Create a new virtual machine



New Virtual Machine Wizard


Options
You can create a new virtual machine or add an existing one to the Virtual PC Console.

Select an option:

- Create a virtual machine**
This option guides you through the basic configurations necessary for creating a new virtual machine.
- Use default settings to create a virtual machine**
You can automatically create a .vmc file with default settings. The resulting virtual machine will not have a virtual hard disk associated with it, so you will have to select one using the Settings dialog.
- Add an existing virtual machine**
You can add a virtual machine to the Virtual PC Console from existing .vmc files.

< Back Next > Cancel

Name it:



New Virtual Machine Wizard

Virtual Machine Name and Location
The name you specify will appear in the list of virtual machines in the Virtual PC Console.

Type the name for the virtual machine file. Choose a name that will help you identify this virtual machine's hardware or software configuration or which operating system it will run. The file is automatically saved to the My Virtual Machines folder. To save it to a different location, use the Browse button.

Name and location:
 Browse...

< Back Next > Cancel

General Networking

Choose your operating system, if you are not sure – go for 'other'

New Virtual Machine Wizard

Operating System
Select the operating system you plan to install on this virtual machine.


Selecting an operating system here allows the wizard to recommend appropriate settings for this virtual machine. If the desired guest operating system is not listed, select an operating system that requires an equivalent amount of memory or select Other.

Operating system: **Other** (dropdown menu open showing: Windows 98, Windows NT Workstation, Windows 2000, Windows XP, OS/2, Windows Vista, Windows NT Server, Windows 2000 Server, Windows Server 2003, Other)


Default hardware selection:
Memory: 128 MB
Virtual disk: 16,384 MB
Sound: Sound Blaster 16 compatible

< Back Next > Cancel

Change RAM, for Windows 7 give it at least 512MB




New hard disk:



General Networking

Give it at least 40GB



You are done. Finish, start a virtual machine and load an image:

